

Functions

Wednesday, October 14, 15

Terms

```
void foo() {  
    int a, b;  
    ...  
    bar(a, b);  
}
```

```
void bar(int x, int y) {  
    ...  
}
```

- foo is the *caller*
- bar is the *callee*
- a, b are the *actual parameters* to bar
- x, y are the *formal parameters* of bar
- Shorthand:
 - *argument* = actual parameter
 - *parameter* = formal parameter

Wednesday, October 14, 15

Different kinds of parameters

- Value parameters
- Reference parameters
- Result parameters
- Read-only parameters

Wednesday, October 14, 15

Value parameters

- “Call-by-value”
- Used in C, Java, default in C++
- Passes the value of an argument to the function
- Makes a copy of argument when function is called
- Advantages? Disadvantages?

Wednesday, October 14, 15

Value parameters

```
int x = 1;  
void main () {  
    foo(x, x);  
    print(x);  
}  
  
void foo(int y, int z) {  
    y = 2;  
    z = 3;  
    print(x);  
}
```

Wednesday, October 14, 15

Value parameters

```
int x = 1;  
void main () {  
    foo(x, x);  
    print(x);  
}  
  
void foo(int y, int z) {  
    y = 2;  
    z = 3;  
    print(x);  
}
```

- What do the print statements print?

Wednesday, October 14, 15

Value parameters

```
int x = 1;
void main () {
    foo(x, x);
    print(x);
}
```

```
void foo(int y, int z) {
    y = 2;
    z = 3;
    print(x);
}
```

- What do the print statements print?

- Answer:

```
print(x); //prints 1
```

```
print(x); //prints 1
```

Wednesday, October 14, 15

Reference parameters

- “Call-by-reference”
- Optional in Pascal (use “var” keyword) and C++ (use “&”)
- Pass the *address* of the argument to the function
- If an argument is an expression, evaluate it, place it in memory and then pass the address of the memory location
- Advantages? Disadvantages?

Wednesday, October 14, 15

Reference parameters

```
int x = 1;
void main () {
    foo(x, x);
    print(x);
}
```

```
void foo(int &y, int &z) {
    y = 2;
    z = 3;
    print(x);
    print(y);
}
```

Wednesday, October 14, 15

Reference parameters

```
int x = 1;
void main () {
    foo(x, x);
    print(x);
}
```

```
void foo(int &y, int &z) {
    y = 2;
    z = 3;
    print(x);
    print(y);
}
```

- What do the print statements print?

Wednesday, October 14, 15

Reference parameters

```
int x = 1;
void main () {
    foo(x, x);
    print(x);
}
```

```
void foo(int &y, int &z) {
    y = 2;
    z = 3;
    print(x);
    print(y);
}
```

- What do the print statements print?

- Answer:

```
print(x); //prints 3
```

```
print(x); //prints 3
```

```
print(y); //prints 3!
```

Wednesday, October 14, 15

Result parameters

- Return values of a function
- Some languages let you specify other parameters as result parameters – these are un-initialized at the beginning of the function
- Copied at the end of function into the arguments of the caller
- C++ supports “return references”

```
int& foo( ... )
```

compute return values, store in memory, return address of return value

Wednesday, October 14, 15

Result parameters

```
int x = 1;
void main () {
    foo(x, x);
    print(x);
}

void foo(int y, result int z) {
    y = 2;
    z = 3;
    print(x);
}
```

Wednesday, October 14, 15

Result parameters

```
int x = 1;
void main () {
    foo(x, x);
    print(x);
}

void foo(int y, result int z) {
    y = 2;
    z = 3;
    print(x);
}
```

- What do the print statements print?

Wednesday, October 14, 15

Result parameters

```
int x = 1;
void main () {
    foo(x, x);
    print(x);
}

void foo(int y, result int z) {
    y = 2;
    z = 3;
    print(x);
}
```

- What do the print statements print?
- Answer:
print(x); //prints 3
print(x); //prints 1

Wednesday, October 14, 15

Read only parameters

- Used when callee will not change value of parameters
- Read-only restriction must be enforced by compiler
- This can be tricky when in the presence of aliasing and control flow

```
void foo(const int x, int y) {
    int * p;
    if (...) p = &x else p = &y
    *p = 4
}
```

- Is this legal? Hard to tell!
 - gcc will not let the assignment happen

Wednesday, October 14, 15

Esoteric: "name" parameters

- "Call-by-name"
 - Usually, we evaluate the arguments before passing them to the function. In call-by-name, the arguments are passed to the function before evaluation
 - Not used in many languages, but Haskell uses a variant

```
int x = 2;
void main () {
    foo(x + 2);
}

void foo(int y) {
    z = y + 2;
    print(z);
}
```

→

```
int x = 2;
void main () {
    foo(x + 2);
}

void foo(int y) {
    z = x + 2 + 2;
    print(z);
}
```

Wednesday, October 14, 15

Why is this useful?

```
int x = 2;
void main () {
    foo(bar());
}

void foo(int y) {
    if ( ... ) {
        z = y;
    } else {
        z = 3;
    }
    print(z);
}
```

- Consider the code on the left
- Normally, we must evaluate bar() before calling foo()
- But what if bar() runs for a long time?
- In call by name, we only evaluate bar() if we need to use it

Wednesday, October 14, 15

Other considerations

- Scalars
 - For call by value, can pass the address of the actual parameter and copy the value into local storage within the procedure
 - Reduces size of caller code (why is this good?)
- For machines with a lot of registers (e.g., MIPS), compilers will save a few registers for arguments and return types
- Less need to manipulate stack


Wednesday, October 14, 15

Other considerations

- Arrays
 - For efficiency reasons, arrays should be passed by reference (why?)
 - Java, C, C++ pass arrays by reference by default (technically, they pass a pointer to the array by value)
- Pass in a fixed size dope vector as the actual parameter (not the whole array!)
- Callee can copy array into local storage as needed


Wednesday, October 14, 15

Function call behavior




Wednesday, October 14, 15

Function call behavior




Wednesday, October 14, 15

Function call behavior



Wednesday, October 14, 15


Function call behavior



Wednesday, October 14, 15

Function call behavior

call stack



```
main() {
    foo();
    ...
}

foo() {
    bar();
    ...
    baz();
}
```



Wednesday, October 14, 15

Calling a function

- What should happen when a function is called?
- Set the *frame pointer* (sets the base of the activation record)
- Allocate space for local variables (use the function's symbol table for this)
- What about registers?
- Callee might want to use registers that the caller is using


Wednesday, October 14, 15

Saving registers

- Two options: *caller saves* and *callee saves*
- Caller saves
 - Caller pushes all the registers it is using on to the stack before calling function, restores the registers after the function returns
- Callee saves
 - Callee pushes all the registers it is *going to use* on the stack immediately after being called, restores the registers just before it returns
- Why use one vs. the other?
- Simple optimizations are good here: don't save registers if the caller/callee doesn't use any

Wednesday, October 14, 15

Activation records



Is this record generated for callee-saves or caller-saves? How would the other record look?

Wednesday, October 14, 15

The frame pointer

- Manipulate with instructions like `link` and `unlink`
- `link`: push current value of FP on to stack, set FP to top of stack
- `unlink`: read value at current address pointed to by FP, set FP to point to that value
- In other words: `link` pushes a new frame onto the stack, `unlink` pops it off

Wednesday, October 14, 15

Example Subroutine Call and Stack Frame

Lower addr


```
z = SubOne(x,2*y);
```

```
int SubOne(int a, int b) {
    int l1, l2;
    l1 = a;
    l2 = b;
    return l1+l2;
};
```

24

Wednesday, October 14, 15


Example Subroutine Call and Stack Frame



```
z = SubOne(x,2*y);
```

```
int SubOne(int a, int b) {
    int l1, l2;
    l1 = a;
    l2 = b;
    return l1+l2;
};
```

Example Subroutine Call and Stack Frame



3-address code:


```
push
push x
mul 2 y t1
push t1
jsr SubOne
pop
pop z
```

```
z = SubOne(x,2*y);
```

```
int SubOne(int a, int b) {
    int l1, l2;
    l1 = a;
    l2 = b;
    return l1+l2;
};
```

```
link 3
move $P1 $L1
move $P2 $L2
add $L1 $L2 l2
move l2 $R
unlink
ret
```

Example Subroutine Call and Stack Frame



3-address code:

```
push
push x
mul 2 y t1
push t1
jsr SubOne
pop
pop z
```

assembly code:

```
push
push x
load y R1
mul 2 R1
push R1
jsr SubOne
pop
pop R1
store R1 z
```

```
z = SubOne(x,2*y);
```

```
int SubOne(int a, int b) {
    int l1, l2;
    l1 = a;
    l2 = b;
    return l1+l2;
};
```

```
link 3
move $P1 $L1
move $P2 $L2
add $L1 $L2 l2
move l2 $R
unlink
ret
```

```
link R6 3
load 3(R6) R1
store R1 -1(R6)
load 2(R6) R2
store R2 -2(R6)
load -1(R6) R1
add -2(R6) R1
store R1 4(R6)
unlink
ret
```